

## Step 1: Installing Python

You'll need to make sure you have the necessary python libraries. The algorithm is implemented in and tested against Python version 3.6. The Anaconda distribution of Python is recommended, but any distribution with the appropriate packages will work. You can download Anaconda here: <https://www.continuum.io/downloads>

### Required Packages

Anaconda comes bundled with all of the required packages except GDAL. A full list of required packages is included below.

gdal v2.0+	numpy	scipy	h5py
skimage	sklearn	matplotlib	tkinter

## Step 2: Installing GDAL

### Mac and Linux Instructions

- 1) Open the terminal application
- 2) Make sure your path variable is set to point at the anaconda install location. If you installed Anaconda in Step 1, this should already be done. You can test this by typing:

```
conda info
```

If this returns information about the anaconda install, you're good to go. Otherwise (i.e. it returns something similar to "-bash: conda: command not found", find the install location of anaconda and add that directory to the path variable. If you installed anaconda in </Users/your\_name/anaconda>, you would enter:

```
export PATH=/Users/your_name/anaconda/bin:$PATH
```

- 3) Type: "conda install gdal" and press enter.
  - a. If this fails due to administrative privileges, type:

```
sudo conda install gdal
```
  - b. This will prompt you for the administrator password; enter it.
- 4) Once the install is complete, enter:

```
export GDAL_DATA=/Users/your_name/anaconda/share/gdal
```

assuming you installed anaconda to </Users/your\_name/anaconda>.

### Windows Instructions

- 1) Open Anaconda Prompt. This will have been installed as part of Anaconda.
- 2) Type: "conda install gdal" at the command line.

- a. Note that you will likely need administrative privileges for this step. This can be accomplished by right clicking the Anaconda Prompt icon and selecting “Run as Administrator”. Alternatively, find the Anaconda install directory, right click on the folder, select properties and click the security tab. Highlight "Users\..." in the upper pane, and check full control" in the second. Select Apply.

3) The program should download the gdal components and install.

### Step 3: Creating an Appropriate File Structure

If you are comfortable running scripts from the command line and you know the directory of the images you wish to process, you can skip to Step 4.

The example below will demonstrate creating an appropriate file structure that can help to get the process running quickly. We will use specific directory names for demonstration, though the file and folder names and locations are not required to be the same as below.

1. Set up a folder on your computer to contain the code and all images you are interested in processing. If you are on Windows, we will use the path ‘C:\Image\_Processing’. If you are on a Mac, we will demonstrate with ‘/Users/name/Image\_Processing’ (note: Replace ‘name’ with the appropriate name for your system).
2. Place the file containing the image processing scripts into this folder.
  - a. If you downloaded the scripts from github, these should be contained in a folder named “OSSP”.
  - b. If you were provided a .zip file containing the code, extract this file here.
3. There should be three training dataset files included with the code:
  - a. icebridge\_training\_dataset.h5
  - b. wv02\_training\_dataset.h5
  - c. pan\_training\_dataset.h5

As their names suggest, each of these files contain training data for a specific type of image.

4. Place the images you wish to process into a subdirectory. On Windows, place the files in ‘C:\Image\_Processing\Images’, on Mac: ‘/Users/name/Image\_Processing/Images’.

### Step 4: Processing the Imagery

The easiest way to get started with the algorithm is to use the ‘ossprocess.py’ script to analyze all of the imagery in a given folder using the provided training datasets. In the advanced section, we will explore methods for creating custom training datasets and processing an image one step at a time.

1. Windows: Open the Anaconda Prompt that is installed with Anaconda  
Mac: Open the Terminal app

2. Change directory to the location of the script. Following from the example above, type:

Windows: `cd C:\Image_Processing\OSSP`

Mac: `cd /Users/name/Image_Processing/OSSP`

3. Compile the cython libraries: The first step is to run the setup.py script to compile C libraries. Run “`python setup.py build_ext --build-lib .`” from the OSSP directory. Be sure to include the period after --build-lib.
4. Run the script to process the images you placed in the ‘Images’ folder. Following our example from step 3, enter on one line:

Windows:

```
python ossp_process.py C:\Image_Processing\Images srgb  
.\training_datasets\icebridge_v3_training_data.h5 -v
```

Mac:

```
python ossp_process.py /Users/name/Image_Processing/Images srgb  
./training_datasets/icebridge_v3_training_data.h5 -v
```

Understanding the arguments of the ossp\_process.py script can permit the user to generate commands that process images of different types, in different locations, and using different training datasets. The following shows a generic script call:

```
python ossp_process.py <input_directory> <image_type>  
<training_data_file> --splits --parallel
```

Required Arguments:

- **input directory:** directory containing all of the images you wish to process  
Note that all .jpg and .tif images in the input directory as well as all sub-directories of it will be processed.
- **image type:** the type of imagery you are processing
  - a. options: {'srgb', 'wv02\_ms', 'pan'}  
respectively representing RGB imagery taken by a typical camera, Worldview 2 multispectral imagery, and high resolution panchromatic imagery.
- **training dataset file:** complete filepath of the training dataset you wish to use to analyze the input imagery

Optional Arguments:

- **-t | --threads:** Number of subprocesses to spawn for classification. Threads > 2 is only utilized for images larger than ~10,000x10,000 pixels.
- **-v | --verbose:** Print progress updates as code executes.
- **--training\_label:** the label of a custom training dataset. See advanced section for details.  
Default = **image type**.

## Advanced Usage

### Creating your own training dataset:

The relevant script for this process is "training\_gui.py". Here's how it works:

Place the images you want to use to create your new training set in their own folder. For illustration, we will use the directory: "C:\Image\_Processing\Training\_Images". We will also assume you are using sRGB images (if not, substitute the appropriate `image_type` argument).

In the same way that you ran the batch process script, type: `python training_gui.py C:\Image_Processing\Training_Images srgb`

This should bring up a welcome window. Click on the 'Initialize Image' button to begin. Segments are presented randomly and are indicated by the highlighted region. If you wish to label a specific segment, click on any of the three image windows and the GUI will change to the segment under the mouse click.

**Note:** If the number next to "Total Progress" is not 0, that means the script found an existing training set. You can either continue with the existing one (adding new data) or create a new set. To create a new set, exit the GUI and rerun it with either the `--username` option or the `--training_data` option pointing to a nonexistent file. If you create a new dataset with name "elephants" (for example), you will need to add `--training_label elephants` when you call the `ossp_process.py` script.

Quotation marks around the directory are needed if there are any spaces in the folder names.

### Supplement:

Supported imagery formats:

- 1) sRGB
- 2) Panchromatic
- 3) 8-band pansharpened (i.e. WorldView 2)

### DISCLAIMER:

The algorithm has been tested with .jpg and .tif(f) formatted files only. **ossp\_process.py will only work with folders of .jpg and .tif(f) files.** Any imagery format readable by GDAL should work when processing images individually, though other formats have not been tested.